



Étape 1:

Ouvrir Windows Mail. Cliquer sur "Outils" et sélectionner "Comptes".

📑 Inbox - Windows Mail		
File Edit View	Tools Message Help	
📑 Create Mail 🔻	Send and Receive	
 Local Folders Inbox Outbox Sent Item Deleted It Drafts Junk E-ma Microsoft Co 	Synchronize All	
	Windows Contacts Add Sender to Contacts	Ctrl+Shift+C
	Windows Calendar	Ctrl+Shift+L
	Message Rules	•
	Newsgroups	Ctrl+W
	Accounts	
	Junk E-mail Options Options	

Étape 2:

Sélectionner le compte de messagerie que vous souhaitez configurer pour l'authentification du serveur de courrier sortant. Cliquer sur "**Propriétés**".



Étape 3:

Cliquer sur l'onglet 'Servers'. Cocher "Mon serveur requiert une authentification". Sélectionner l'onglet "Avancé".

🐌 pop.citenet.net Properties		
General Servers Connection	Security Advanced	
Server Information My incoming mail server is	a POP3 server.	
Incoming mail (POP3): pop.citenet.net		
Outgoing mail (SMTP): smtp.citenet.net		
Incoming Mail Server		
E-mail username:	jsmith@citenet.net	
Password:		
	Remember password	
Log on using Secure Pas	ssword Authentication	
Outgoing Mail Server		
✓ My server requires auther	entication Settings	
	OK Cancel Apply	

Étape 4:

Changer le serveur sortant (SMTP) par le numéro de port 587 et Cliquer sur **OK** au bas de cette fenêtre.

🐉 pop.citenet.net Properties			
General Servers Connection Security Advanced			
Server Port Numbers			
Outgoing mail (SMTP): 587 Use Defaults			
This server requires a secure connection (SSL)			
Incoming mail (POP3): 110			
This server requires a secure connection (SSL)			
Server Timeouts			
Short 🐨 Long 1 minute			
Sending			
Break apart messages larger than 60 KB			
Delivery			
Leave a copy of messages on server			
Remove from server after 5 day(s)			
Remove from server when deleted from 'Deleted Items'			
OK Cancel Apply			

Étape 5:

Cliquer sur "Terminer".